
PyREx Documentation

Release 1.1.1

Ben Hokanson-Fasig

Nov 13, 2017

CONTENTS:

1	Introduction to PyREx	1
1.1	Installation	1
1.2	Code Example	1
1.3	Units	2
2	Code Examples	3
2.1	Working with Signal Objects	3
2.2	Antenna Class and Subclasses	6
2.3	Ice and Earth Models	8
2.4	Particle Generation	9
2.5	Ray Tracing	9
2.6	Full Simulation	10
2.7	More Examples	11
3	PyREx API	13
3.1	Package contents	13
3.2	Submodules	17
3.2.1	pyrex.signals module	17
3.2.2	pyrex.antenna module	19
3.2.3	pyrex.ice_model module	20
3.2.4	pyrex.earth_model module	21
3.2.5	pyrex.particle module	21
3.2.6	pyrex.ray_tracing module	22
3.2.7	pyrex.kernel module	22
3.2.8	pyrex.custom module	22
4	Version History	25
4.1	Version 1.1.2	25
4.2	Version 1.1.1	25
4.3	Version 1.1.0	25
4.4	Version 1.0.3	26
4.5	Version 1.0.2	26
4.6	Version 1.0.1	26
4.7	Version 1.0.0	26
4.8	Version 0.0.0	27
	Python Module Index	29
	Index	31

INTRODUCTION TO PYREX

PyREx (**P**ython package for an IceCube **R**adio **E**xtension) is, as its name suggests, a python package designed to simulate the measurement of Askaryan pulses via a radio antenna array around the IceCube South Pole Neutrino Observatory. The code is designed to be modular so that it can also be applied to other askaryan radio antennas, as in the ARA and ARIANA collaborations.

1.1 Installation

To use the PyREx package, download the code from <https://github.com/bhokansonfasig/pyrex> and then either include the `pyrex` directory (the one containing the python modules) in your `PYTHON_PATH`, or just copy the `pyrex` directory into your working directory. In the future, PyREx may be installable via `pip`, but it is not currently available there.

1.2 Code Example

The most basic simulation can be produced as follows:

First, import the package:

```
import pyrex
```

Then, create a particle generator object that will produce random particles in a cube of 1 km on each side with a fixed energy of 100 PeV:

```
particle_generator = pyrex.ShadowGenerator(dx=1000, dy=1000, dz=1000,  
                                           energy_generator=lambda: 1e8)
```

An array of antennas that represent the detector is also needed. The base `Antenna` class provides a basic antenna with a flat frequency response and no trigger condition. Here we make a single vertical “string” of four antennas with no noise:

```
antenna_array = []  
for z in [-100, -150, -200, -250]:  
    antenna_array.append(  
        pyrex.Antenna(position=(0,0,z), noisy=False)  
    )
```

Finally, we want to pass these into the `EventKernel` and produce an event:

```
kernel = pyrex.EventKernel(generator=particle_generator,
                           ice_model=pyrex.IceModel, antennas=antenna_array)
kernel.event()
```

Now the signals received by each antenna can be accessed by their `waveforms` parameter:

```
import matplotlib.pyplot as plt
for ant in kernel.ant_array:
    for wave in ant.waveforms:
        plt.figure()
        plt.plot(wave.times, wave.values)
        plt.show()
```

1.3 Units

For ease of use, PyREx tries to use consistent units in all classes and functions. The units used are mostly SI with a few exceptions listed in bold below:

Metric	Unit
time	seconds (s)
frequency	hertz (Hz)
distance	meters (m)
density	grams per cubic centimeter (g/cm³)
material thickness	grams per square centimeter (g/cm²)
temperature	kelvin (K)
energy	gigaelectronvolts (GeV)
resistance	ohms (Ω)
voltage	volts (V)
electric field	volts per meter (V/m)

CODE EXAMPLES

The following code examples assume these imports:

```
import numpy as np
import matplotlib.pyplot as plt
import scipy.fftpack
import pyrex
```

All of the following examples can also be found (and quickly run) in the Code Examples python notebook.

2.1 Working with Signal Objects

The base `Signal` class is simply an array of times and an array of signal values, and is instantiated with these two arrays. The `times` array is assumed to be in units of seconds, but there are no general units for the `values` array. It is worth noting that the `Signal` object stores shallow copies of the passed arrays, so changing the original arrays will not affect the `Signal` object.

```
time_array = np.linspace(0, 10)
value_array = np.sin(time_array)
my_signal = pyrex.Signal(times=time_array, values=value_array)
```

Plotting the `Signal` object is as simple as plotting the times vs the values:

```
plt.plot(my_signal.times, my_signal.values)
plt.show()
```

While there are no specified units for a `Signal.values`, there is the option to specify the `value_type` of the values. This is done using the `Signal.ValueTypes` enum. By default, a `Signal` object has `value_type=ValueTypes.unknown`. However, if the signal represents a voltage, electric field, or electric power; `value_type` can be set to `Signal.ValueTypes.voltage`, `Signal.ValueTypes.field`, or `Signal.ValueTypes.power` respectively:

```
my_voltage_signal = pyrex.Signal(times=time_array, values=value_array,
                                value_type=pyrex.Signal.ValueTypes.voltage)
```

`Signal` objects can be added as long as they have the same time array and `value_type`. `Signal` objects also support the python `sum` function:

```
time_array = np.linspace(0, 10)
values1 = np.sin(time_array)
values2 = np.cos(time_array)
signal1 = pyrex.Signal(time_array, values1)
```

```
plt.plot(signal1.times, signal1.values, label="signal1 = sin(t)")
signal2 = pyrex.Signal(time_array, values2)
plt.plot(signal2.times, signal2.values, label="signal2 = cos(t)")
signal3 = signal1 + signal2
plt.plot(signal3.times, signal3.values, label="signal3 = sin(t)+cos(t)")
all_signals = [signal1, signal2, signal3]
signal4 = sum(all_signals)
plt.plot(signal4.times, signal4.values, label="signal4 = 2*(sin(t)+cos(t))")
plt.legend()
plt.show()
```

The `Signal` class provides many convenience attributes for dealing with signals:

```
my_signal.dt == my_signal.times[1] - my_signal.times[0]
my_signal.spectrum == scipy.fftpack.fft(my_signal.values)
my_signal.frequencies == scipy.fftpack.fftfreq(n=len(my_signal.values),
                                              d=my_signal.dt)
my_signal.envelope == np.abs(scipy.signal.hilbert(my_signal.values))
```

The `Signal` class also provides functions for manipulating the signal. The `resample` function will resample the times and values arrays to the given number of points (with the same endpoints):

```
my_signal.resample(1001)
len(my_signal.times) == len(my_signal.values) == 1001
my_signal.times[0] == 0
my_signal.times[-1] == 10
plt.plot(my_signal.times, my_signal.values)
plt.show()
```

The `with_times` function will interpolate/extrapolate the signal's values onto a new times array:

```
new_times = np.linspace(-5, 15)
new_signal = my_signal.with_times(new_times)
plt.plot(new_signal.times, new_signal.values, label="new signal")
plt.plot(my_signal.times, my_signal.values, label="original signal")
plt.legend()
plt.show()
```

The `filter_frequencies` function will apply a frequency-domain filter to the values array based on the passed frequency response function:

```
def lowpass_filter(frequency):
    if frequency < 1:
        return 1
    else:
        return 0

time_array = np.linspace(0, 10, 1001)
value_array = np.sin(0.1*2*np.pi*time_array) + np.sin(2*2*np.pi*time_array)
my_signal = pyrex.Signal(times=time_array, values=value_array)

plt.plot(my_signal.times, my_signal.values)
my_signal.filter_frequencies(lowpass_filter)
plt.plot(my_signal.times, my_signal.values)
plt.show()
```

A number of classes which inherit from the `Signal` class are included in PyREx: `EmptySignal`,

FunctionSignal, AskaryanSignal, and ThermalNoise. EmptySignal is simply a signal whose values are all zero:

```
time_array = np.linspace(0,10)
empty = pyrex.EmptySignal(times=time_array)
plt.plot(empty.times, empty.values)
plt.show()
```

FunctionSignal takes a function of time and creates a signal based on that function:

```
time_array = np.linspace(0, 10, num=101)
def square_wave(time):
    if int(time)%2==0:
        return 1
    else:
        return -1
square_signal = pyrex.FunctionSignal(times=time_array, function=square_wave)
plt.plot(square_signal.times, square_signal.values)
plt.show()
```

Additionally, FunctionSignal leverages its knowledge of the function to more accurately interpolate and extrapolate values for the with_times function:

```
new_times = np.linspace(0, 20, num=201)
long_square_signal = square_signal.with_times(new_times)
plt.plot(long_square_signal.times, long_square_signal.values, label="new signal")
plt.plot(square_signal.times, square_signal.values, label="original signal")
plt.legend()
plt.show()
```

AskaryanSignal produces an Askaryan pulse (in V/m) on a time array due to a neutrino of given energy observed at a given angle from the shower axis:

```
time_array = np.linspace(-10e-9, 40e-9, 1001)
neutrino_energy = 1e8 # GeV
observation_angle = 45 * np.pi/180 # radians
askaryan = pyrex.AskaryanSignal(times=time_array, energy=neutrino_energy,
                                theta=observation_angle)
print(askaryan.value_type)
plt.plot(askaryan.times, askaryan.values)
plt.show()
```

ThermalNoise produces Rayleigh noise (in V) at a given temperature and resistance which has been passed through a bandpass filter of the given frequency range:

```
time_array = np.linspace(-10e-9, 40e-9, 1001)
noise_temp = 300 # K
system_resistance = 1000 # ohm
frequency_range = (550e6, 750e6) # Hz
noise = pyrex.ThermalNoise(times=time_array, temperature=noise_temp,
                            resistance=system_resistance,
                            f_band=frequency_range)
print(noise.value_type)
plt.plot(noise.times, noise.values)
plt.show()
```

Note that since ThermalNoise inherits from FunctionSignal, it can be extrapolated nicely to new times. It may be highly periodic outside of its original time range however, unless a large number of frequencies is requested

on initialization.

```
short_noise = pyrex.ThermalNoise(times=time_array, temperature=noise_temp,
                                resistance=system_resistance,
                                f_band=(100e6, 400e6))
long_noise = short_noise.with_times(np.linspace(-10e-9, 90e-9, 2001))

plt.plot(short_noise.times, short_noise.values)
plt.show()
plt.plot(long_noise.times, long_noise.values)
plt.show()
```

2.2 Antenna Class and Subclasses

The base Antenna class provided by PyREx is designed to be inherited from to match the needs of each project. At its core, an Antenna object is initialized with a position, a temperature, and a frequency range, as well as optionally a resistance for noise calculations and a boolean dictating whether or not noise should be added to the antenna's signals (note that if noise is to be added, a resistance must be specified).

```
# Please note that some values are unrealistic in order to simplify demonstration
position = (0, 0, -100) # m
temperature = 300 # K
resistance = 1e17 # ohm
frequency_range = (0, 5) # Hz
basic_antenna = pyrex.Antenna(position=position, temperature=temperature,
                              resistance=resistance,
                              freq_range=frequency_range)
noiseless_antenna = pyrex.Antenna(position=position, noisy=False)
```

The basic properties of an Antenna object are `is_hit` and `waveforms`. `is_hit` specifies whether or not the antenna has been triggered by an event. `waveforms` is a list of all the waveforms which have triggered the antenna. The antenna also defines `signals`, which is a list of all signals the antenna has received, and `all_waveforms` which is a list of all waveforms (signal plus noise) the antenna has received including those which didn't trigger.

```
basic_antenna.is_hit == False
basic_antenna.waveforms == []
```

The Antenna class contains two attributes and three methods which represent characteristics of the antenna as they relate to signal processing. The attributes are `efficiency` and `antenna_factor`, and the methods are `response`, `directional_gain`, and `polarization_gain`. The attributes are to be set and the methods overwritten in order to customize the way the antenna responds to incoming signals. `efficiency` is simply a scalar which multiplies the signal the antenna receives (default value is 1). `antenna_factor` is a factor used in converting received electric fields into voltages ($\text{antenna_factor} = E / V$; default value is 1). `response` takes a frequency or list of frequencies (in Hz) and returns the frequency response of the antenna at each frequency given (default always returns 1). `directional_gain` takes angles `theta` and `phi` in the antenna's coordinates and returns the antenna's gain for a signal coming from that direction (default always returns 1). Finally, `polarization_gain` takes a polarization vector and returns the antenna's gain for a signal with that polarization (default always returns 1).

```
basic_antenna.efficiency == 1
basic_antenna.antenna_factor == 1
freqs = [1, 2, 3, 4, 5]
basic_antenna.response(freqs) == [1, 1, 1, 1, 1]
basic_antenna.directional_gain(theta=np.pi/2, phi=0) == 1
basic_antenna.polarization_gain([0,0,1]) == 1
```

The `Antenna` class defines a `trigger` method which is also expected to be overwritten. `trigger` takes a `Signal` object as an argument and returns a boolean of whether or not the antenna would trigger on that signal (default always returns `True`).

```
basic_antenna.trigger(pyrex.Signal([0],[0])) == True
```

The `Antenna` class also defines a `receive` method which takes a `Signal` object and processes the signal according to the antenna's attributes (efficiency, `antenna_factor`, `response`, `directional_gain`, and `polarization_gain` as described above). To use the `receive` function, simply pass it the `Signal` object the antenna sees, and the `Antenna` class will handle the rest. You can also optionally specify the origin point of the signal (used in `directional_gain` calculation) and the polarization direction of the signal (used in `polarization_gain` calculation). If either of these is unspecified, the corresponding gain will simply be set to 1.

```
incoming_signal_1 = pyrex.FunctionSignal(np.linspace(0,2*np.pi), np.sin,
                                         value_type=pyrex.Signal.ValueTypes.voltage)
incoming_signal_2 = pyrex.FunctionSignal(np.linspace(4*np.pi,6*np.pi), np.sin,
                                         value_type=pyrex.Signal.ValueTypes.voltage)
basic_antenna.receive(incoming_signal_1)
basic_antenna.receive(incoming_signal_2, origin=[0,0,-300], polarization=[1,0,0])
basic_antenna.is_hit == True
for waveform, pure_signal in zip(basic_antenna.waveforms, basic_antenna.signals):
    plt.figure()
    plt.plot(waveform.times, waveform.values, label="Waveform")
    plt.plot(pure_signal.times, pure_signal.values, label="Pure Signal")
    plt.legend()
    plt.show()
```

Beyond `Antenna.waveforms`, the `Antenna` object also provides methods for checking the waveform and trigger status for arbitrary times: `full_waveform` and `is_hit_during`. Both of these methods take a time array as an argument and return the waveform `Signal` object for those times and whether said waveform triggered the antenna, respectively.

```
total_waveform = basic_antenna.full_waveform(np.linspace(0,20))
plt.plot(total_waveform.times, total_waveform.values, label="Total Waveform")
plt.plot(incoming_signal_1.times, incoming_signal_1.values, label="Pure Signals")
plt.plot(incoming_signal_2.times, incoming_signal_2.values, color="C1")
plt.legend()
plt.show()

basic_antenna.is_hit_during(np.linspace(0, 200e-9)) == True
```

Finally, the `Antenna` class defines a `clear` method which will reset the antenna to a state of having received no signals:

```
basic_antenna.clear()
basic_antenna.is_hit == False
len(basic_antenna.waveforms) == 0
```

To create a custom antenna, simply inherit from the `Antenna` class:

```
class NoiselessThresholdAntenna(pyrex.Antenna):
    def __init__(self, position, threshold):
        super().__init__(position=position, noisy=False)
        self.threshold = threshold

    def trigger(self, signal):
```

```
if max(np.abs(signal.values)) > self.threshold:
    return True
else:
    return False
```

Our custom NoiselessThresholdAntenna should only trigger when the amplitude of a signal exceeds its threshold value:

```
my_antenna = NoiselessThresholdAntenna(position=(0, 0, 0), threshold=2)

incoming_singal = pyrex.FunctionSignal(np.linspace(0,10), np.sin,
                                       value_type=pyrex.Signal.ValueTypes.voltage)

my_antenna.receive(incoming_singal)
my_antenna.is_hit == False
len(my_antenna.waveforms) == 0
len(my_antenna.all_waveforms) == 1

incoming_singal = pyrex.Signal(incoming_singal.times,
                               5*incoming_singal.values,
                               incoming_singal.value_type)
my_antenna.receive(incoming_singal)
my_antenna.is_hit == True
len(my_antenna.waveforms) == 1
len(my_antenna.all_waveforms) == 2

for wave in my_antenna.waveforms:
    plt.figure()
    plt.plot(wave.times, wave.values)
    plt.show()
```

PyREx defines DipoleAntenna which as a subclass of Antenna, which provides a basic threshold trigger, a basic bandpass filter frequency response, a sine-function directional gain, and a typical dot-product polarization effect. A DipoleAntenna object is created as follows:

```
antenna_identifier = "antenna 1"
position = (0, 0, -100)
center_frequency = 250e6 # Hz
bandwidth = 300e6 # Hz
resistance = 100 # ohm
antenna_length = 3e8/center_frequency/2 # m
polarization_direction = (0, 0, 1)
trigger_threshold = 1e-5 # V
dipole = pyrex.DipoleAntenna(name=antenna_identifier, position=position,
                             center_frequency=center_frequency,
                             bandwidth=bandwidth, resistance=resistance,
                             effective_height=antenna_length,
                             orientation=polarization_direction,
                             trigger_threshold=trigger_threshold)
```

2.3 Ice and Earth Models

PyREx provides a class IceModel, which is an alias for whichever south pole ice model class is the preferred (currently just the basic AntarcticIce). The IceModel class provides class methods for calculating characteristics of the ice at different depths and frequencies outlined below:

```
depth = -1000 # m
pyrex.IceModel.temperature(depth)
pyrex.IceModel.index(depth)
pyrex.IceModel.gradient(depth)
frequency = 1e8 # Hz
pyrex.IceModel.attenuation_length(depth, frequency)
```

PyREx also provides two functions related to its earth model: `prem_density` and `slant_depth`. `prem_density` calculates the density in grams per cubic centimeter of the earth at a given radius:

```
radius = 6360000 # m
pyrex.prem_density(radius)
```

`slant_depth` calculates the material thickness in grams per square centimeter of a chord cutting through the earth at a given nadir angle, starting from a given depth:

```
nadir_angle = 60 * np.pi/180 # radians
depth = 1000 # m
pyrex.slant_depth(nadir_angle, depth)
```

2.4 Particle Generation

PyREx includes `Particle` as a container for information about neutrinos which are generated to produce Askaryan pulses. `Particle` contains three attributes: `vertex`, `direction`, and `energy`:

```
initial_position = (0,0,0) # m
direction_vector = (0,0,-1)
particle_energy = 1e8 # GeV
pyrex.Particle(vertex=initial_position, direction=direction_vector,
               energy=particle_energy)
```

PyREx also includes a `ShadowGenerator` class for generating random neutrinos, taking into account some Earth shadowing. The neutrinos are generated in a box of given size, and with an energy given by an energy generation function:

```
box_width = 1000 # m
box_depth = 500 # m
const_energy_generator = lambda: 1e8 # GeV
my_generator = pyrex.ShadowGenerator(dx=box_width, dy=box_width,
                                     dz=box_depth,
                                     energy_generator=const_energy_generator)
my_generator.create_particle()
```

2.5 Ray Tracing

While PyREx does not currently support full ray tracing, it does provide a `PathFinder` class which implements some basic ray analysis by Snell's law. `PathFinder` takes an ice model and two points as arguments and provides a number of properties and methods regarding the path between the points.

```
start = (0, 0, -100) # m
finish = (0, 0, -250) # m
```

```
my_path = pyrex.PathFinder(ice_model=pyrex.IceModel,
                           from_point=start, to_point=finish)
```

`PathFinder.exists` is a boolean value of whether or not the path between the points is traversable according to the indices of refraction. `PathFinder.emitted_ray` is a unit vector giving the direction from `from_point` to `to_point`. `PathFinder.path_length` is the length in meters of the straight line path between the two points.

```
my_path.exists
my_path.emitted_ray
my_path.path_length
```

`PathFinder.time_of_flight()` calculates the time it takes for light to traverse the path, with an optional parameter `n_steps` defining the precision used. `PathFinder.tof` is a convenience property set to the time of flight using the default value of `n_steps`.

```
my_path.time_of_flight(n_steps=100)
my_path.time_of_flight() == my_path.tof
```

`PathFinder.attenuation()` calculates the attenuation factor along the path for a signal of given frequency. Here again there is an optional parameter `n_steps` defining the precision used.

```
frequency = 1e9 # Hz
my_path.attenuation(f=frequency, n_steps=100)
```

Finally, `PathFinder.propagate()` propagates a `Signal` object from `from_point` to `to_point` by applying a $1/\text{PathFinder.path_length}$ factor, applying the frequency attenuation of `PathFinder.attenuation()`, and shifting the signal times by `PathFinder.tof`:

```
time_array = np.linspace(0, 5e-9, 1001)
my_signal = (pyrex.FunctionSignal(time_array, lambda t: np.sin(1e9*2*np.pi*t))
            + pyrex.FunctionSignal(time_array, lambda t: np.sin(1e10*2*np.pi*t)))
plt.plot(my_signal.times, my_signal.values)
plt.show()

my_path.propagate(my_signal)
plt.plot(my_signal.times, my_signal.values)
plt.show()
```

2.6 Full Simulation

PyREx provides the `EventKernel` class to control a basic simulation including the creation of neutrinos, the propagation of their pulses to the antennas, and the triggering of the antennas:

```
particle_generator = pyrex.ShadowGenerator(dx=1000, dy=1000, dz=500,
                                           energy_generator=lambda: 1e8)
detector = []
for i, z in enumerate([-100, -150, -200, -250]):
    detector.append(
        pyrex.DipoleAntenna(name="antenna_"+str(i), position=(0, 0, z),
                           center_frequency=250e6, bandwidth=300e6,
                           resistance=0, effective_height=0.6,
                           trigger_threshold=0, noisy=False)
    )
kernel = pyrex.EventKernel(generator=particle_generator,
```

```
        ice_model=pyrex.IceModel,
        antennas=detector)

triggered = False
while not triggered:
    kernel.event()
    for antenna in detector:
        if antenna.is_hit:
            triggered = True
            break

for antenna in detector:
    for i, wave in enumerate(antenna.waveforms):
        plt.plot(wave.times * 1e9, wave.values)
        plt.xlabel("Time (ns)")
        plt.ylabel("Voltage (V)")
        plt.title(antenna.name + " - waveform " + str(i))
```

2.7 More Examples

For more code examples, see the PyREx Demo python notebook.

3.1 Package contents

class `pyrex.Signal` (*times, values, value_type=<ValueTypes.undefined: 0>*)

Base class for signals. Takes arrays of times and values (values array forced to size of times array by zero padding or slicing). Supports adding between signals with the same time values, resampling the signal, and calculating the signal's envelope.

class `ValueTypes`

Enum containing possible types (units) for signal values.

undefined = 0

voltage = 1

field = 2

power = 3

dt

Returns the spacing of the time array, or None if invalid.

envelope

Calculates envelope of the signal by Hilbert transform.

resample (*n*)

Resamples the signal into *n* points in the same time range.

with_times (*new_times*)

Returns a signal object representing this signal with a different times array. Uses `numpy.interp` on values by default.

spectrum

Returns the FFT spectrum of the signal.

frequencies

Returns the FFT frequencies of the signal.

filter_frequencies (*freq_response*)

Applies the given frequency response function to the signal.

class `pyrex.EmptySignal` (*times, value_type=<ValueTypes.undefined: 0>*)

Bases: `pyrex.signals.Signal`

Class for signal with no amplitude (all values = 0)

with_times (*new_times*)

Returns a signal object representing this signal with a different times array. Returns `EmptySignal` for new times.

class `pyrex.FunctionSignal` (*times, function, value_type=<ValueTypes.undefined: 0>*)

Bases: `pyrex.signals.Signal`

Class for signals generated by a function

with_times (*new_times*)

Returns a signal object representing this signal with a different times array. Leverages knowledge of the function to properly interpolate and extrapolate.

`pyrex.AskaryanSignal`

alias of `FastAskaryanSignal`

class `pyrex.signals.FastAskaryanSignal` (*times, energy, theta, n=1.78, t0=0*)

Bases: `pyrex.signals.Signal`

Askaryan pulse binned to times from neutrino with given energy (GeV) observed at angle theta (radians). Optional parameters are the index of refraction n, and pulse offset to start time t0 (s). Returned signal values are electric fields (V/m).

Note that the amplitude of the pulse goes as 1/R, where R is the distance from source to observer. R is assumed to be 1 meter so that dividing by a different value produces the proper result.

vector_potential

Recover the vector_potential from the electric field. Mostly just for testing purposes.

RAC (*time*)

Calculates $R * \text{vector potential (A)}$ at the Cherenkov angle in Vs at the given time (s).

charge_profile (*z, density=0.92, crit_energy=0.0786, rad_length=36.08*)

Calculates the longitudinal charge profile in the EM shower at distance z (m) with parameters for the density (g/cm^3), critical energy (GeV), and electron radiation length (g/cm^2) in ice.

max_length (*density=0.92, crit_energy=0.0786, rad_length=36.08*)

Calculates the maximum length (m) of an EM shower with parameters for the density (g/cm^3), critical energy (GeV), and electron radiation length (g/cm^2) in ice.

class `pyrex.ThermalNoise` (*times, f_band, f_amplitude=1, rms_voltage=None, temperature=None, resistance=None, n_freqs=0*)

Bases: `pyrex.signals.FunctionSignal`

Thermal Rayleigh noise in the frequency band `f_band=[f_min, f_max]` (Hz) at a given temperature (K) and resistance (ohms) or with a given RMS voltage (V). Optional parameters are `f_amplitude` (default 1) which can be a number or a function designating the amplitudes at each frequency, and `n_freqs` which is the number of frequencies to use (in `f_band`) for the calculation (default is based on the FFT bin size of the given times array). Returned signal values are voltages (V).

class `pyrex.Antenna` (*position, z_axis=[0, 0, 1], x_axis=[1, 0, 0], antenna_factor=1, efficiency=1, freq_range=None, noise_rms=None, temperature=None, resistance=None, noisy=True*)

Base class for an antenna with a given position (m), temperature (K), allowable frequency range (Hz), total resistance (ohm) used for Johnson noise, and whether or not to include noise in the antenna's waveforms. Defines default trigger, frequency response, and signal reception functions that can be overwritten in base classes to customize the antenna.

is_hit

Test for whether the antenna has been triggered.

is_hit_during (*times*)

Test for whether the antenna has been triggered during the given times array.

clear ()

Reset the antenna to a state of having received no signals.

waveforms

Signal + noise (if noisy) at each triggered antenna hit.

all_waveforms

Signal + noise (if noisy) at all antenna hits, even those that didn't trigger.

full_waveform (*times*)

Signal + noise (if noisy) for the given times array.

make_noise (*times*)

Returns the noise signal generated by the antenna over the given array of times. Used to add noise to signal for production of the antenna's waveforms.

trigger (*signal*)

Function to determine whether or not the antenna is triggered by the given Signal object.

directional_gain (*theta*, *phi*)

Function to calculate the directive electric field gain of the antenna at given angles theta (polar) and phi (azimuthal) relative to the antenna's orientation.

polarization_gain (*polarization*)

Function to calculate the electric field gain due to polarization for a given polarization direction.

response (*frequencies*)

Function to return the frequency response of the antenna at the given frequencies (Hz). This function should return the response as imaginary numbers, where the real part is the amplitude response and the imaginary part is the phase response.

receive (*signal*, *origin=None*, *polarization=None*)

Process incoming signal according to the filter function and store it to the signals list. Subclasses may extend this function, but should end with `super().receive(signal)`.

class `pyrex.DipoleAntenna` (*name*, *position*, *center_frequency*, *bandwidth*, *resistance*, *orientation=[0, 0, 1]*, *trigger_threshold=0*, *effective_height=None*, *noisy=True*)

Bases: `pyrex.antenna.Antenna`

Antenna with a given name, position (m), center frequency (Hz), bandwidth (Hz), resistance (ohm), effective height (m), polarization direction, and trigger threshold (V).

trigger (*signal*)

Trigger on the signal if the maximum signal value is above the given threshold.

response (*frequencies*)

Butterworth filter response for the antenna's frequency range.

directional_gain (*theta*, *phi*)

Power gain of dipole antenna goes as $\sin(\theta)^2$, so electric field gain goes as $\sin(\theta)$.

polarization_gain (*polarization*)

Polarization gain is simply the dot product of the polarization with the antenna's z-axis.

`pyrex.IceModel`

alias of `AntarcticIce`

class `pyrex.ice_model.AntarcticIce`

Bases: `object`

Class containing characteristics of ice at the south pole. In all cases, depth *z* is given with negative values in the ice and positive values above the ice.

k = 0.438

a = 0.0132

n0 = 1.32

thickness = 2850

classmethod gradient (*z*)

Returns the gradient of the index of refraction at depth *z* (m).

classmethod index (*z*)

Returns the medium's index of refraction, *n*, at depth *z* (m). Supports passing a numpy array of depths.

static temperature (*z*)

Returns the temperature (K) of the ice at depth *z* (m). Supports passing a numpy array of depths.

classmethod attenuation_length (*z, f*)

Returns the attenuation length at depth *z* (m) and frequency *f* (Hz). Supports passing a numpy array of depths and/or frequencies. If both are passed as arrays, a 2-D array is returned where each row is a single depth and each column is a single frequency.

pyrex.prem_density (*r*)

Returns the earth's density (g/cm³) for a given radius *r* (m). Calculated by the Preliminary Earth Model (PREM).

pyrex.slant_depth (*angle, depth, step=5000*)

Returns the material thickness (g/cm²) for a chord cutting through earth at Nadir angle and starting at depth (m).

class pyrex.Particle (*vertex, direction, energy*)

Class for storing particle attributes. Consists of a 3-D vertex (m), 3-D direction vector (automatically normalized), and an energy (GeV).

class pyrex.ShadowGenerator (*dx, dy, dz, energy_generator*)

Class to generate UHE neutrino vertices in (relatively) shallow detectors. Takes into account Earth shadowing (sort of). *energy_generator* should be a function that returns a particle energy in GeV.

create_particle ()

Creates a particle with random vertex in cube and random direction.

class pyrex.PathFinder (*ice_model, from_point, to_point*)

Class for ray tracking.

exists

Boolean of whether path exists.

emitted_ray

Direction in which ray is emitted.

path_length

Length of the path (m).

tof

Time of flight (s) for a particle along the path. Calculated using default values of `self.time_of_flight()`

time_of_flight (*n_steps=100*)

Time of flight (s) for a particle along the path.

attenuation (*f, n_steps=100*)

Returns the attenuation factor for a signal of frequency *f* (Hz) traveling along the path. Supports passing a list of frequencies.

propagate (*signal*)

Applies attenuation to the signal along the path.

class `pyrex.EventKernel` (*generator, ice_model, antennas*)

Kernel for generation of events with a given particle generator, ice model, and list of antennas.

event ()

Generate particle, propagate signal through ice to antennas, process signal at antennas, and return the original particle.

3.2 Submodules

3.2.1 `pyrex.signals` module

Module containing classes for digital signal processing

class `pyrex.signals.Signal` (*times, values, value_type=<ValueTypes.undefined: 0>*)

Bases: `object`

Base class for signals. Takes arrays of times and values (values array forced to size of times array by zero padding or slicing). Supports adding between signals with the same time values, resampling the signal, and calculating the signal's envelope.

class `ValueTypes`

Bases: `enum.Enum`

Enum containing possible types (units) for signal values.

undefined = 0

voltage = 1

field = 2

power = 3

dt

Returns the spacing of the time array, or None if invalid.

envelope

Calculates envelope of the signal by Hilbert transform.

resample (*n*)

Resamples the signal into n points in the same time range.

with_times (*new_times*)

Returns a signal object representing this signal with a different times array. Uses `numpy.interp` on values by default.

spectrum

Returns the FFT spectrum of the signal.

frequencies

Returns the FFT frequencies of the signal.

filter_frequencies (*freq_response*)

Applies the given frequency response function to the signal.

class `pyrex.signals.EmptySignal` (*times, value_type=<ValueTypes.undefined: 0>*)

Bases: `pyrex.signals.Signal`

Class for signal with no amplitude (all values = 0)

with_times (*new_times*)

Returns a signal object representing this signal with a different times array. Returns EmptySignal for new times.

class `pyrex.signals.FunctionSignal` (*times, function, value_type=<ValueTypes.undefined: 0>*)

Bases: `pyrex.signals.Signal`

Class for signals generated by a function

with_times (*new_times*)

Returns a signal object representing this signal with a different times array. Leverages knowledge of the function to properly interpolate and extrapolate.

class `pyrex.signals.SlowAskaryanSignal` (*times, energy, theta, n=1.78, t0=0*)

Bases: `pyrex.signals.Signal`

Askaryan pulse binned to times from neutrino with given energy (GeV) observed at angle theta (radians). Optional parameters are the index of refraction n, and pulse offset to start time t0 (s). Returned signal values are electric fields (V/m).

Note that the amplitude of the pulse goes as 1/R, where R is the distance from source to observer. R is assumed to be 1 meter so that dividing by a different value produces the proper result.

RAC (*time*)

Calculates $R \cdot \text{vector potential}$ at the Cherenkov angle in Vs at the given time (s).

charge_profile (*z, density=0.92, crit_energy=0.0786, rad_length=36.08*)

Calculates the longitudinal charge profile in the EM shower at distance z (m) with parameters for the density (g/cm^3), critical energy (GeV), and electron radiation length (g/cm^2) in ice.

max_length (*density=0.92, crit_energy=0.0786, rad_length=36.08*)

Calculates the maximum length (m) of an EM shower with parameters for the density (g/cm^3), critical energy (GeV), and electron radiation length (g/cm^2) in ice.

class `pyrex.signals.FastAskaryanSignal` (*times, energy, theta, n=1.78, t0=0*)

Bases: `pyrex.signals.Signal`

Askaryan pulse binned to times from neutrino with given energy (GeV) observed at angle theta (radians). Optional parameters are the index of refraction n, and pulse offset to start time t0 (s). Returned signal values are electric fields (V/m).

Note that the amplitude of the pulse goes as 1/R, where R is the distance from source to observer. R is assumed to be 1 meter so that dividing by a different value produces the proper result.

vector_potential

Recover the vector_potential from the electric field. Mostly just for testing purposes.

RAC (*time*)

Calculates $R \cdot \text{vector potential}$ (A) at the Cherenkov angle in Vs at the given time (s).

charge_profile (*z, density=0.92, crit_energy=0.0786, rad_length=36.08*)

Calculates the longitudinal charge profile in the EM shower at distance z (m) with parameters for the density (g/cm^3), critical energy (GeV), and electron radiation length (g/cm^2) in ice.

max_length (*density=0.92, crit_energy=0.0786, rad_length=36.08*)

Calculates the maximum length (m) of an EM shower with parameters for the density (g/cm^3), critical energy (GeV), and electron radiation length (g/cm^2) in ice.

`pyrex.signals.AskaryanSignal`

alias of `FastAskaryanSignal`

class `pyrex.signals.GaussianNoise` (*times, sigma*)

Bases: `pyrex.signals.Signal`

Gaussian noise signal with standard deviation sigma

```
class pyrex.signals.ThermalNoise (times, f_band, f_amplitude=1, rms_voltage=None, temperature=None, resistance=None, n_freqs=0)
```

Bases: `pyrex.signals.FunctionSignal`

Thermal Rayleigh noise in the frequency band `f_band=[f_min,f_max]` (Hz) at a given temperature (K) and resistance (ohms) or with a given RMS voltage (V). Optional parameters are `f_amplitude` (default 1) which can be a number or a function designating the amplitudes at each frequency, and `n_freqs` which is the number of frequencies to use (in `f_band`) for the calculation (default is based on the FFT bin size of the given times array). Returned signal values are voltages (V).

3.2.2 pyrex.antenna module

Module containing antenna class capable of receiving signals

```
class pyrex.antenna.Antenna (position, z_axis=[0, 0, 1], x_axis=[1, 0, 0], antenna_factor=1, efficiency=1, freq_range=None, noise_rms=None, temperature=None, resistance=None, noisy=True)
```

Bases: `object`

Base class for an antenna with a given position (m), temperature (K), allowable frequency range (Hz), total resistance (ohm) used for Johnson noise, and whether or not to include noise in the antenna's waveforms. Defines default trigger, frequency response, and signal reception functions that can be overwritten in base classes to customize the antenna.

is_hit

Test for whether the antenna has been triggered.

is_hit_during (*times*)

Test for whether the antenna has been triggered during the given times array.

clear ()

Reset the antenna to a state of having received no signals.

waveforms

Signal + noise (if noisy) at each triggered antenna hit.

all_waveforms

Signal + noise (if noisy) at all antenna hits, even those that didn't trigger.

full_waveform (*times*)

Signal + noise (if noisy) for the given times array.

make_noise (*times*)

Returns the noise signal generated by the antenna over the given array of times. Used to add noise to signal for production of the antenna's waveforms.

trigger (*signal*)

Function to determine whether or not the antenna is triggered by the given Signal object.

directional_gain (*theta, phi*)

Function to calculate the directive electric field gain of the antenna at given angles theta (polar) and phi (azimuthal) relative to the antenna's orientation.

polarization_gain (*polarization*)

Function to calculate the electric field gain due to polarization for a given polarization direction.

response (*frequencies*)

Function to return the frequency response of the antenna at the given frequencies (Hz). This function

should return the response as imaginary numbers, where the real part is the amplitude response and the imaginary part is the phase response.

receive (*signal*, *origin=None*, *polarization=None*)

Process incoming signal according to the filter function and store it to the signals list. Subclasses may extend this function, but should end with `super().receive(signal)`.

class `pyrex.antenna.DipoleAntenna` (*name*, *position*, *center_frequency*, *bandwidth*, *resistance*, *orientation=[0, 0, 1]*, *trigger_threshold=0*, *effective_height=None*, *noisy=True*)

Bases: `pyrex.antenna.Antenna`

Antenna with a given name, position (m), center frequency (Hz), bandwidth (Hz), resistance (ohm), effective height (m), polarization direction, and trigger threshold (V).

trigger (*signal*)

Trigger on the signal if the maximum signal value is above the given threshold.

response (*frequencies*)

Butterworth filter response for the antenna's frequency range.

directional_gain (*theta*, *phi*)

Power gain of dipole antenna goes as $\sin(\theta)^2$, so electric field gain goes as $\sin(\theta)$.

polarization_gain (*polarization*)

Polarization gain is simply the dot product of the polarization with the antenna's z-axis.

3.2.3 pyrex.ice_model module

Module containing ice model. `AntarcticIce` class contains static and class methods for easy swapping of models. `IceModel` class is set to the preferred ice model.

class `pyrex.ice_model.AntarcticIce`

Bases: `object`

Class containing characteristics of ice at the south pole. In all cases, depth *z* is given with negative values in the ice and positive values above the ice.

k = 0.438

a = 0.0132

n0 = 1.32

thickness = 2850

classmethod `gradient` (*z*)

Returns the gradient of the index of refraction at depth *z* (m).

classmethod `index` (*z*)

Returns the medium's index of refraction, *n*, at depth *z* (m). Supports passing a numpy array of depths.

static `temperature` (*z*)

Returns the temperature (K) of the ice at depth *z* (m). Supports passing a numpy array of depths.

classmethod `attenuation_length` (*z*, *f*)

Returns the attenuation length at depth *z* (m) and frequency *f* (Hz). Supports passing a numpy array of depths and/or frequencies. If both are passed as arrays, a 2-D array is returned where each row is a single depth and each column is a single frequency.

class `pyrex.ice_model.NewcombIce`

Bases: `pyrex.ice_model.AntarcticIce`

Class inheriting from `AntarcticIce`, with new `attenuation_length` function based on Matt Newcomb's fit (DOESN'T CURRENTLY WORK - USE ANTARCTICICE).

classmethod `attenuation_length(z, f)`

Returns the attenuation length at depth z (m) and frequency f (MHz) by Matt Newcomb's fit (DOESN'T CURRENTLY WORK - USE BOGORODSKY).

`pyrex.ice_model.IceModel`
alias of `AntarcticIce`

3.2.4 pyrex.earth_model module

Module containing earth model. Uses PREM for density as a function of radius and a simple integrator for calculation of the slant depth as a function of nadir angle.

`pyrex.earth_model.prem_density(r)`

Returns the earth's density (g/cm^3) for a given radius r (m). Calculated by the Preliminary Earth Model (PREM).

`pyrex.earth_model.slant_depth(angle, depth, step=5000)`

Returns the material thickness (g/cm^2) for a chord cutting through earth at Nadir angle and starting at depth (m).

3.2.5 pyrex.particle module

Module for particles (namely neutrinos) and neutrino interactions in the ice. Interactions include Earth shadowing (absorption) effect.

class `pyrex.particle.NeutrinoInteraction(c, p)`

Bases: `object`

Class for neutrino interaction attributes.

cross_section(E)

Return the cross section at a given energy E (GeV).

interaction_length(E)

Return the interaction length at a given energy E (GeV).

class `pyrex.particle.Particle(vertex, direction, energy)`

Bases: `object`

Class for storing particle attributes. Consists of a 3-D vertex (m), 3-D direction vector (automatically normalized), and an energy (GeV).

`pyrex.particle.random_direction()`

Generate an arbitrary 3D unit vector.

class `pyrex.particle.ShadowGenerator(dx, dy, dz, energy_generator)`

Bases: `object`

Class to generate UHE neutrino vertices in (relatively) shallow detectors. Takes into account Earth shadowing (sort of). `energy_generator` should be a function that returns a particle energy in GeV.

create_particle()

Creates a particle with random vertex in cube and random direction.

3.2.6 pyrex.ray_tracing module

Module containing class for ray tracking through the ice. Ray tracing not yet implemented.

class `pyrex.ray_tracing.PathFinder` (*ice_model, from_point, to_point*)

Bases: `object`

Class for ray tracking.

exists

Boolean of whether path exists.

emitted_ray

Direction in which ray is emitted.

path_length

Length of the path (m).

tof

Time of flight (s) for a particle along the path. Calculated using default values of `self.time_of_flight()`

time_of_flight (*n_steps=100*)

Time of flight (s) for a particle along the path.

attenuation (*f, n_steps=100*)

Returns the attenuation factor for a signal of frequency *f* (Hz) traveling along the path. Supports passing a list of frequencies.

propagate (*signal*)

Applies attenuation to the signal along the path.

3.2.7 pyrex.kernel module

Module for the simulation kernel. Includes neutrino generation, ray tracking (no raytracing yet), and hit generation.

class `pyrex.kernel.EventKernel` (*generator, ice_model, antennas*)

Bases: `object`

Kernel for generation of events with a given particle generator, ice model, and list of antennas.

event ()

Generate particle, propagate signal through ice to antennas, process signal at antennas, and return the original particle.

3.2.8 pyrex.custom module

Module containing customized classes for IREX

`pyrex.custom.envelope_model` (*signal, cap=2.2e-10, res=50*)

Model of a basic diode-capacitor-resistor envelope circuit. Takes a signal object as the input voltage and returns the output voltage signal object.

class `pyrex.custom.IREXBaseAntenna` (*position, center_frequency, bandwidth, resistance, orientation=(0, 0, 1), effective_height=None, amplification=1, noisy=True*)

Bases: `pyrex.antenna.Antenna`

Antenna to be used in `IREXAntenna` class. Has a position (m), center frequency (Hz), bandwidth (Hz), resistance (ohm), effective height (m), and polarization direction.

response (*frequencies*)

Butterworth filter response for the antenna's frequency range.

directional_gain (*theta, phi*)

Power gain of dipole antenna goes as $\sin(\theta)^2$, so electric field gain goes as $\sin(\theta)$.

polarization_gain (*polarization*)

Polarization gain is simply the dot product of the polarization with the antenna's z-axis.

```
class pyrex.custom.IREXAntenna(name, position, trigger_threshold, time_over_threshold=0,
                              orientation=(0, 0, 1), amplification=1, noisy=True, envelope_method='analytic')
```

Bases: object

IREX antenna system consisting of dipole antenna, low-noise amplifier, optional bandpass filter, and envelope circuit.

change_antenna (*center_frequency=250000000.0, bandwidth=300000000.0, resistance=100, orientation=(0, 0, 1), effective_height=None, amplification=1, noisy=True*)

Changes attributes of the antenna including center frequency (Hz), bandwidth (Hz), resistance (ohms), orientation, and effective height (m).

make_envelope (*signal*)

is_hit

signals

waveforms

all_waveforms

receive (*signal, origin=None, polarization=None*)

clear ()

trigger (*signal*)

```
class pyrex.custom.IREXDetector(number_of_stations, station_separation, antennas_per_string,
                                antenna_separation, lowest_antenna, geometry='grid',
                                strings_per_station=1, string_separation=100)
```

Bases: object

Class for automatically generating antenna positions based on geometry criteria. Takes as arguments the number of stations, the distance between stations, the number of antennas per string, the separation (in z) of the antennas on the string, the position of the lowest antenna, and the name of the geometry to use. Optional parameters (depending on the geometry) are the number of strings per station and the distance from station to string. The `build_antennas` method is responsible for actually placing antennas at the generated positions, after which the class can be directly iterated to iterate over the antennas.

build_antennas (*trigger_threshold, time_over_threshold=0, naming_scheme=<function IREXDetector.<lambda>>, polarization_scheme=<function IREXDetector.<lambda>>, noisy=True, envelope_method='analytic'*)

Sets up IREXAntennas at the positions stored in the class. Takes as arguments the trigger threshold, optional time over threshold, and whether to add noise to the waveforms. Other optional arguments include a naming scheme and polarization scheme which are functions taking the antenna index *i* and the antenna object and should return the name and polarization of the antenna, respectively.

VERSION HISTORY

4.1 Version 1.1.2

- Added `with_times` method to `Signal` class for interpolation/extrapolation of signals to different times.
- Change `Antenna.make_noise` to use a single master noise object and use `with_times` to calculate noise at different times.
 - To ensure noise is not obviously periodic (for <100 signals), uses 100 times the recommended number of frequencies, which results in longer computation time for noise waveforms.
- Add `full_waveform` and `is_hit_during` methods to `Antenna` class for calculation of waveform over arbitrary time array and whether said waveform triggers the antenna, respectively.

4.2 Version 1.1.1

- Moved `ValueTypes` inside `Signal` class. Now access as `Signal.ValueTypes.voltage`, etc.
- Changed signal envelope calculation in custom `IREXAntenna` from hilbert transform to a basic model. Spice model also available, but slower.

4.3 Version 1.1.0

- Made units consistent across PyREx.
- Added `directional_gain` and `polarization_gain` methods to base `Antenna`.
 - `receive` method should no longer be overwritten in most cases.
 - `Antenna` now has orientation defined by `z_axis` and `x_axis`.
 - `antenna_factor` and `efficiency` attributes added to `Antenna` for more flexibility.
- Added ability to define `Antenna` noise by RMS voltage rather than temperature and resistance if desired.
- Added `value_type` attribute to `Signal` class and derived classes.
 - Current value types are `ValueTypes.undefined`, `ValueTypes.voltage`, `ValueTypes.field`, and `ValueTypes.power`.
 - `Signal` objects now must have the same `value_type` to be added (though those with `ValueTypes.undefined` can be coerced).
- Allow `DipoleAntenna` to guess at `effective_height` if not specified.

- Increase speed of `IceModel.__atten_coeffs` method, resulting in increased speed of attenuation length calculations.

4.4 Version 1.0.3

- Added `custom` module to contain classes and functions specific to the IREX project.

4.5 Version 1.0.2

- Allow passing of numpy arrays of depths and frequencies into most `IceModel` methods.
 - `IceModel.gradient()` must still be calculated at individual depths.
- Added ability to specify RMS voltage of `ThermalNoise` without providing temperature and resistance.
- Removed (deprecated) `Antenna.isHit()`.
- Added `Antenna.make_noise()` method so custom antennas can use their own noise functions.
- Performance improvements:
 - Allowing for `IceModel` to calculate many attenuation lengths at once improves speed of `PathFinder.propagate()`.
 - Improved speed of `PathFinder.time_of_flight()` and `PathFinder.attenuation()` (and improved accuracy to boot).

4.6 Version 1.0.1

- Fixed bugs in `AskaryanSignal` that caused the convolution to fail.
- Changed `Antenna` not require a temperature and frequency range if no noise is produced.
- Fixed bugs resulting from converting `IceModel.temperature()` from Celsius to Kelvin.

4.7 Version 1.0.0

- Created PyREx package based on original notebook.
- Added all signal classes to produce full-waveform Askaryan pulses and thermal noise.
- Changed `Antenna` class to `DipoleAntenna` to allow `Antenna` to be a base class.
- Changed `Antenna.isHit()` method to `Antenna.is_hit` property.
- Introduced `IceModel` alias for `AntarcticIce` (or any future preferred ice model).
- Moved `AntarcticIce.attenuationLengthMN` to its own `NewcombIce` class inheriting from `AntarcticIce`.
- Added `PathFinder.propagate()` to propagate a `Signal` object in a customizable way.
- Changed naming conventions to be more consistent, verbose, and “pythonic”:
 - `AntarcticIce.attenuationLength()` becomes `AntarcticIce.attenuation_length()`.

- In `pyrex.earth_model`, `RE` becomes `EARTH_RADIUS`.
- In `pyrex.particle`, `neutrino_interaction` becomes `NeutrinoInteraction`.
- In `pyrex.particle`, `NA` becomes `AVOGADRO_NUMBER`.
- `particle` class becomes `Particle` `namedtuple`.
 - * `Particle.vtx` becomes `Particle.vertex`.
 - * `Particle.dir` becomes `Particle.direction`.
 - * `Particle.E` becomes `Particle.energy`.
- In `pyrex.particle`, `next_direction()` becomes `random_direction()`.
- `shadow_generator` becomes `ShadowGenerator`.
- `PathFinder` methods become properties where reasonable:
 - * `PathFinder.exists()` becomes `PathFinder.exists`.
 - * `PathFinder.getEmittedRay()` becomes `PathFinder.emitted_ray`.
 - * `PathFinder.getPathLength()` becomes `PathFinder.path_length`.
- `PathFinder.propagateRay()` split into `PathFinder.time_of_flight()` (with corresponding `PathFinder.tof` property) and `PathFinder.attenuation()`.

4.8 Version 0.0.0

Original PyREx python notebook written by Kael Hanson:

<https://gist.github.com/physkael/898a64e6fbf5f0917584c6d31edf7940>

PYTHON MODULE INDEX

p

- `pyrex`, [13](#)
- `pyrex.antenna`, [19](#)
- `pyrex.custom`, [22](#)
- `pyrex.earth_model`, [21](#)
- `pyrex.ice_model`, [20](#)
- `pyrex.kernel`, [22](#)
- `pyrex.particle`, [21](#)
- `pyrex.ray_tracing`, [22](#)
- `pyrex.signals`, [17](#)

A

a (pyrex.ice_model.AntarcticIce attribute), 15, 20
 all_waveforms (pyrex.Antenna attribute), 15
 all_waveforms (pyrex.antenna.Antenna attribute), 19
 all_waveforms (pyrex.custom.IREXAntenna attribute), 23
 AntarcticIce (class in pyrex.ice_model), 15, 20
 Antenna (class in pyrex), 14
 Antenna (class in pyrex.antenna), 19
 AskaryanSignal (in module pyrex), 14
 AskaryanSignal (in module pyrex.signals), 18
 attenuation() (pyrex.PathFinder method), 16
 attenuation() (pyrex.ray_tracing.PathFinder method), 22
 attenuation_length() (pyrex.ice_model.AntarcticIce class method), 16, 20
 attenuation_length() (pyrex.ice_model.NewcombIce class method), 21

B

build_antennas() (pyrex.custom.IREXDetector method), 23

C

change_antenna() (pyrex.custom.IREXAntenna method), 23
 charge_profile() (pyrex.signals.FastAskaryanSignal method), 14, 18
 charge_profile() (pyrex.signals.SlowAskaryanSignal method), 18
 clear() (pyrex.Antenna method), 14
 clear() (pyrex.antenna.Antenna method), 19
 clear() (pyrex.custom.IREXAntenna method), 23
 create_particle() (pyrex.particle.ShadowGenerator method), 21
 create_particle() (pyrex.ShadowGenerator method), 16
 cross_section() (pyrex.particle.NeutrinoInteraction method), 21

D

DipoleAntenna (class in pyrex), 15
 DipoleAntenna (class in pyrex.antenna), 20
 directional_gain() (pyrex.Antenna method), 15

directional_gain() (pyrex.antenna.Antenna method), 19
 directional_gain() (pyrex.antenna.DipoleAntenna method), 20
 directional_gain() (pyrex.custom.IREXBaseAntenna method), 23
 directional_gain() (pyrex.DipoleAntenna method), 15
 dt (pyrex.Signal attribute), 13
 dt (pyrex.signals.Signal attribute), 17

E

emitted_ray (pyrex.PathFinder attribute), 16
 emitted_ray (pyrex.ray_tracing.PathFinder attribute), 22
 EmptySignal (class in pyrex), 13
 EmptySignal (class in pyrex.signals), 17
 envelope (pyrex.Signal attribute), 13
 envelope (pyrex.signals.Signal attribute), 17
 envelope_model() (in module pyrex.custom), 22
 event() (pyrex.EventKernel method), 17
 event() (pyrex.kernel.EventKernel method), 22
 EventKernel (class in pyrex), 16
 EventKernel (class in pyrex.kernel), 22
 exists (pyrex.PathFinder attribute), 16
 exists (pyrex.ray_tracing.PathFinder attribute), 22

F

FastAskaryanSignal (class in pyrex.signals), 14, 18
 field (pyrex.Signal.ValueTypes attribute), 13
 field (pyrex.signals.Signal.ValueTypes attribute), 17
 filter_frequencies() (pyrex.Signal method), 13
 filter_frequencies() (pyrex.signals.Signal method), 17
 frequencies (pyrex.Signal attribute), 13
 frequencies (pyrex.signals.Signal attribute), 17
 full_waveform() (pyrex.Antenna method), 15
 full_waveform() (pyrex.antenna.Antenna method), 19
 FunctionSignal (class in pyrex), 13
 FunctionSignal (class in pyrex.signals), 18

G

GaussianNoise (class in pyrex.signals), 18
 gradient() (pyrex.ice_model.AntarcticIce class method), 16, 20

I

IceModel (in module pyrex), 15
IceModel (in module pyrex.ice_model), 21
index() (pyrex.ice_model.AntarcticIce class method), 16, 20
interaction_length() (pyrex.particle.NeutrinoInteraction method), 21
IREXAntenna (class in pyrex.custom), 23
IREXBaseAntenna (class in pyrex.custom), 22
IREXDetector (class in pyrex.custom), 23
is_hit (pyrex.Antenna attribute), 14
is_hit (pyrex.antenna.Antenna attribute), 19
is_hit (pyrex.custom.IREXAntenna attribute), 23
is_hit_during() (pyrex.Antenna method), 14
is_hit_during() (pyrex.antenna.Antenna method), 19

K

k (pyrex.ice_model.AntarcticIce attribute), 15, 20

M

make_envelope() (pyrex.custom.IREXAntenna method), 23
make_noise() (pyrex.Antenna method), 15
make_noise() (pyrex.antenna.Antenna method), 19
max_length() (pyrex.signals.FastAskaryanSignal method), 14, 18
max_length() (pyrex.signals.SlowAskaryanSignal method), 18

N

n0 (pyrex.ice_model.AntarcticIce attribute), 15, 20
NeutrinoInteraction (class in pyrex.particle), 21
NewcombIce (class in pyrex.ice_model), 20

P

Particle (class in pyrex), 16
Particle (class in pyrex.particle), 21
path_length (pyrex.PathFinder attribute), 16
path_length (pyrex.ray_tracing.PathFinder attribute), 22
PathFinder (class in pyrex), 16
PathFinder (class in pyrex.ray_tracing), 22
polarization_gain() (pyrex.Antenna method), 15
polarization_gain() (pyrex.antenna.Antenna method), 19
polarization_gain() (pyrex.antenna.DipoleAntenna method), 20
polarization_gain() (pyrex.custom.IREXBaseAntenna method), 23
polarization_gain() (pyrex.DipoleAntenna method), 15
power (pyrex.Signal.ValueTypes attribute), 13
power (pyrex.signals.Signal.ValueTypes attribute), 17
prem_density() (in module pyrex), 16
prem_density() (in module pyrex.earth_model), 21
propagate() (pyrex.PathFinder method), 16

propagate() (pyrex.ray_tracing.PathFinder method), 22
pyrex (module), 13
pyrex.antenna (module), 19
pyrex.custom (module), 22
pyrex.earth_model (module), 21
pyrex.ice_model (module), 20
pyrex.kernel (module), 22
pyrex.particle (module), 21
pyrex.ray_tracing (module), 22
pyrex.signals (module), 17

R

RAC() (pyrex.signals.FastAskaryanSignal method), 14, 18
RAC() (pyrex.signals.SlowAskaryanSignal method), 18
random_direction() (in module pyrex.particle), 21
receive() (pyrex.Antenna method), 15
receive() (pyrex.antenna.Antenna method), 20
receive() (pyrex.custom.IREXAntenna method), 23
resample() (pyrex.Signal method), 13
resample() (pyrex.signals.Signal method), 17
response() (pyrex.Antenna method), 15
response() (pyrex.antenna.Antenna method), 19
response() (pyrex.antenna.DipoleAntenna method), 20
response() (pyrex.custom.IREXBaseAntenna method), 22
response() (pyrex.DipoleAntenna method), 15

S

ShadowGenerator (class in pyrex), 16
ShadowGenerator (class in pyrex.particle), 21
Signal (class in pyrex), 13
Signal (class in pyrex.signals), 17
Signal.ValueTypes (class in pyrex), 13
Signal.ValueTypes (class in pyrex.signals), 17
signals (pyrex.custom.IREXAntenna attribute), 23
slant_depth() (in module pyrex), 16
slant_depth() (in module pyrex.earth_model), 21
SlowAskaryanSignal (class in pyrex.signals), 18
spectrum (pyrex.Signal attribute), 13
spectrum (pyrex.signals.Signal attribute), 17

T

temperature() (pyrex.ice_model.AntarcticIce static method), 16, 20
ThermalNoise (class in pyrex), 14
ThermalNoise (class in pyrex.signals), 19
thickness (pyrex.ice_model.AntarcticIce attribute), 16, 20
time_of_flight() (pyrex.PathFinder method), 16
time_of_flight() (pyrex.ray_tracing.PathFinder method), 22
tof (pyrex.PathFinder attribute), 16
tof (pyrex.ray_tracing.PathFinder attribute), 22
trigger() (pyrex.Antenna method), 15
trigger() (pyrex.antenna.Antenna method), 19

`trigger()` (`pyrex.antenna.DipoleAntenna` method), 20
`trigger()` (`pyrex.custom.IREXAntenna` method), 23
`trigger()` (`pyrex.DipoleAntenna` method), 15

U

`undefined` (`pyrex.Signal.ValueTypes` attribute), 13
`undefined` (`pyrex.signals.Signal.ValueTypes` attribute), 17

V

`vector_potential` (`pyrex.signals.FastAskaryanSignal` attribute), 14, 18
`voltage` (`pyrex.Signal.ValueTypes` attribute), 13
`voltage` (`pyrex.signals.Signal.ValueTypes` attribute), 17

W

`waveforms` (`pyrex.Antenna` attribute), 14
`waveforms` (`pyrex.antenna.Antenna` attribute), 19
`waveforms` (`pyrex.custom.IREXAntenna` attribute), 23
`with_times()` (`pyrex.EmptySignal` method), 13
`with_times()` (`pyrex.FunctionSignal` method), 14
`with_times()` (`pyrex.Signal` method), 13
`with_times()` (`pyrex.signals.EmptySignal` method), 17
`with_times()` (`pyrex.signals.FunctionSignal` method), 18
`with_times()` (`pyrex.signals.Signal` method), 17