PyREx Documentation

Release 1.0.1

Ben Hokanson-Fasig

CONTENTS:

I	Intro	roduction								1
2	2.1 2.2 2.3 2.4 2.5 2.6 2.7	de Examples Working with Signal Objects	 	 	 · · · · · · · · · · · · · · · · · · ·	· · · · · · · · · · · · · · · · · · ·		 	· · · · · ·	3 3 5 7 8 8 9
3	PyRl 3.1 3.2	Package contents		 	 		 			11 11 14 14 16 17 17 18 18
4 Py	4.1 4.2 4.3	Sion History Version 1.0.1 Version 1.0.0 Version 0.0.0 Module Index	 	 	 		 	 		21 21 21 22 23
In	dex									25

CHAPTER

ONE

INTRODUCTION

PyREx (**Py**thon package for an IceCube **R**adio **Ex**tension) is, as its name suggests, a python package designed to simulate the measurement of Askaryan pulses via a radio antenna array around the IceCube South Pole Neutrino Observatory. The code is designed to be modular so that it can also be applied to other askaryan radio antennas, as in the ARA and ARIANA collaborations.

The most basic simulation can be produced as follows:

First, import the package:

```
import pryex
```

Then, create a particle generator object that will produce random particles in a cube of 1 km on each side with a fixed energy of 100 PeV:

An array of antennas that represent the detector is also needed. The base Antenna class provides a basic antenna with a flat frequency response and no trigger condition. Here we make a single vertical "string" of four antennas with no additional noise:

Finally, we want to pass these into the EventKernel and produce an event:

Now the signals received by each antenna can be accessed by their waveforms parameter:

```
import matplotlib.pyplot as plt
for ant in kernel.ant_array:
    for wave in ant.waveforms:
        plt.figure()
        plt.plot(wave.times, wave.values)
        plt.show()
```

CHAPTER

TWO

CODE EXAMPLES

The following code examples assume these imports:

```
import numpy as np
import matplotlib.pyplot as plt
import pyrex
```

All of the following examples can also be found (and quickly run) in the Code Examples python notebook.

2.1 Working with Signal Objects

The base Signal class is simply an array of times and an array of signal values, and is instantiated with these two arrays. The times array is assumed to be in units of seconds, but there are no general units for the values array (though it is commonly assumed to be in volts or volts per meter). It is worth noting that the Singal object stores shallow copies of the passed arrays, so changing the original arrays will not affect the Signal object.

```
time_array = np.linspace(0, 10)
value_array = np.sin(time_array)
my_signal = pyrex.Signal(times=time_array, values=value_array)
```

Plotting the Signal object is as simple as plotting the times vs the values:

```
plt.plot(my_signal.times, my_signal.values)
```

Signal objects can be added as long as they have the same time array, and also support the python sum function:

```
time_array = np.linspace(0, 10)
values1 = np.sin(time_array)
values2 = np.cos(time_array)
signal1 = pyrex.Signal(time_array, values1)
plt.plot(signal1.times, signal1.values, label="signal1")
signal2 = pyrex.Signal(time_array, values2)
plt.plot(signal2.times, signal2.values, label="signal2")
signal3 = signal1 + signal2
plt.plot(signal3.times, signal3.values, label="signal3")
all_signals = [signal1, signal2, signal3]
signal4 = sum(all_signals)
plt.plot(signal4.times, signal4.values, label="signal4")
plt.legend()
```

The Signal class provides many convenience attributes for dealing with signals:

The Signal class also provides functions for manipulating the signal. The resample function will resample the times and values arrays to the given number of points (with the same endpoints):

```
my_signal.resample(1001)
len(my_signal.times) == len(my_signal.values) == 1001
my_signal.times[0] == 0
my_signal.times[-1] == 10
```

The filter_frequencies function will apply a frequency-domain filter to the values array based on the passed frequency response function:

```
def lowpass_filter(frequency):
    if frequency < 1:
        return 1
    else:
        return 0

time_array = np.linspace(0, 10, 1001)
value_array = np.sin(0.1*2*np.pi*time_array) + np.sin(2*2*np.pi*time_array)
my_signal = pyrex.Signal(times=time_array, values=value_array)

plt.plot(my_signal.times, my_signal.values)
my_signal.filter_frequencies(lowpass_filter)
plt.plot(my_signal.times, my_signal.values)</pre>
```

A number of classes which inherit from the Signal class are included in PyREx: EmptySignal, FunctionSignal, AskaryanSignal, and ThermalNoise. EmptySignal is simply a signal whose values are all zero:

```
time_array = np.linspace(0,10)
empty = pyrex.EmptySignal(times=time_array)
plt.plot(empty.times, empty.values)
```

FunctionSignal takes a function of time and creates a signal based on that function:

```
time_array = np.linspace(0,10)
def square_wave(time):
   if int(time)%2==0:
        return 1
   else:
        return -1
square_signal = pyrex.FunctionSignal(times=time_array, function=square_wave)
plt.plot(square_signal.times, square_signal.values)
```

AskaryanSignal produces an Askaryan pulse on a time array due to a neutrino of given energy observed at a given angle from the shower axis:

```
time_array = np.linspace(-10e-9, 40e-9, 1001)
neutrino_energy = 1e5 # TeV
observation_angle = 45 * np.pi/180 # radians
askaryan = pyrex.AskaryanSignal(times=time_array, energy=neutrino_energy,
```

```
theta=observation_angle)
plt.plot(askaryan.times, askaryan.values)
```

ThermalNoise produces Rayleigh noise at a given temperature and resistance which has been passed through a bandpass filter of the given frequency range:

2.2 Antenna Class and Subclasses

The base Antenna class provided by PyREx is designed to be inherited from to match the needs of each project. At its core, an Antenna object is initialized with a position, a temperature, and a frequency range, as well as optionally a resistance for noise calculations and a boolean dictating whether or not noise should be added to the antenna's signals (note that if noise is to be added, a resistance must be specified).

The basic properties of an Antenna object are is_hit and waveforms. is_hit specifies whether or not the antenna has been triggered by an event. waveforms is a list of all the waveforms which have triggered the antenna. The antenna also defines signals, which is a list of all signals the antenna has received, and all_waveforms which is a list of all waveforms (signal plus noise) the antenna has received including those which didn't trigger.

```
basic_antenna.is_hit == False
basic_antenna.waveforms == []
```

The Antenna class defines three methods which are expected to be overwritten: trigger, response, and receive. trigger takes a Signal object as an argument and returns a boolean of whether or not the antenna would trigger on that signal (default always returns True). response takes a frequency or list of frequencies (in Hz) and returns the frequency response of the antenna at each frequency given (default always returns 1).

```
basic_antenna.trigger(pyrex.Signal([0],[0])) == True
freqs = [1, 2, 3, 4, 5]
basic_antenna.response(freqs) == [1, 1, 1, 1, 1]
```

The receive method is a bit different in that it contains some default functionality:

```
def receive(self, signal):
    copy = Signal(signal.times, signal.values)
    copy.filter_frequencies(self.response)
    self.signals.append(copy)
```

In this sense, the receive function is intended to be extended instead of overwritten. In derived classes, it is recommended that a newly defined receive function call super().receive(signal). For example, if a polarization is to be applied, the following receive function could be implemented:

To use the receive function, simply pass it the Signal object the antenna sees, and the Antenna class will handle the rest:

```
incoming_singal = pyrex.FunctionSignal(np.linspace(0,10), np.sin)
basic_antenna.receive(incoming_singal)
basic_antenna.is_hit == True
for wave in basic_antenna.waveforms:
    plt.figure()
    plt.plot(wave.times, wave.values)
    plt.show()
for pure_signal in basic_antenna.signals:
    plt.figure()
    plt.plot(pure_signal.times, pure_signal.values)
    plt.show()
```

The Antenna class also defines a clear method which will reset the antenna to a state of having received no signals:

```
basic_antenna.clear()
basic_antenna.is_hit == False
len(basic_antenna.waveforms) == 0
```

To create a custom antenna, simply inherit from the Antenna class:

```
class NoiselessThresholdAntenna(pyrex.Antenna):
    def __init__(self, position, threshold):
        super().__init__(position=position, noisy=False)
        self.threshold = threshold

def trigger(self, signal):
    if max(np.abs(signal.values)) > self.threshold:
        return True
    else:
        return False
```

Our custom NoiselessThresholdAntenna should only trigger when the amplitude of a signal exceeds its threshold value:

```
my_antenna.is_hit == True
len(my_antenna.waveforms) == 1
len(my_antenna.all_waveforms) == 2

for wave in my_antenna.waveforms:
    plt.figure()
    plt.plot(wave.times, wave.values)
    plt.show()
```

PyREx defines DipoleAntenna which as a subclass of Antenna, which provides a basic threshold trigger, a basic bandpass filter, and a polarization effect on the reception of a signal. A DipoleAntenna object is created as follows:

2.3 Ice and Earth Models

PyREx provides a class IceModel, which is an alias for whichever south pole ice model class is the preferred (currently just the basic AntarcticIce). The IceModel class provides class methods for calculating characteristics of the ice at different depths and frequencies outlined below:

```
depth = -1000 # m
pyrex.IceModel.temperature(depth)
pyrex.IceModel.index(depth)
pyrex.IceModel.gradient(depth)
frequency = 100 # MHz
pyrex.IceModel.attenuation_length(depth, frequency)
```

PyREx also provides two functions realted to its earth model: prem_density and slant_depth. prem_density calculates the density in grams per cubic centimeter of the earth at a given radius:

```
radius = 6360000 # m
pyrex.prem_density(radius)
```

slant_depth calculates the material thickness in grams per square centimeter of a chord cutting through the earth at a given nadir angle, starting from a given depth:

```
nadir_angle = 60 * np.pi/180 # radians
depth = 1000 # m
pyrex.slant_depth(nadir_angle, depth)
```

2.4 Particle Generation

PyREx includes Particle as a container for information about neutrinos which are generated to produce Askaryan pulses. Particle contains three attributes: vertex, direction, and energy:

PyREx also includes a ShadowGenerator class for generating random neutrinos, taking into account some Earth shadowing. The neutrinos are generated in a box of given size, and with an energy given by an energy generation function:

2.5 Ray Tracing

While PyREx does not currently support full ray tracing, it does provide a PathFinder class which implements some basic ray analysis by Snell's law. PathFinder takes an ice model and two points as arguments and provides a number of properties and methods regarding the path between the points.

PathFinder.exists is a boolean value of whether or not the path between the points is traversable according to the indices of refraction. PathFinder.emitted_ray is a unit vector giving the direction from from_point to to point. PathFinder.path length is the length in meters of the straight line path between the two points.

```
my_path.exists
my_path.emitted_ray
my_path.path_length
```

PathFinder.time_of_flight() calculates the time it takes for light to traverse the path, with an optional parameter n_steps defining the precision used. PathFinder.tof is a convenience property set to the time of flight using the default value of n_steps.

```
my_path.time_of_flight(n_steps=100)
my_path.time_of_flight() == my_path.tof
```

PathFinder.attenuation() calculates the attenuation factor along the path for a signal of given frequency. Here again there is an optional parameter n_steps defining the precision used.

```
frequency = 1000 # Hz
my_path.attenuation(f=frequency, n_steps=100)
```

Finally, PathFinder.propagate() propagates a Signal object from from_point to to_point by applying a 1/PathFinder.path_length factor, applying the frequency attenuation of PathFinder. attenuation(), and shifting the signal times by PathFinder.tof:

2.6 Full Simulation

PyREx provides the EventKernel class to control a basic simulation including the creation of neutrinos, the propagation of their pulses to the antennas, and the triggering of the antennas:

```
particle_generator = pyrex.ShadowGenerator(dx=1000, dy=1000, dz=500,
                                           energy_generator=lambda: 1e8)
detector = []
for i, z in enumerate([-100, -150, -200, -250]):
   detector.append(
       pyrex.DipoleAntenna(name="antenna_"+str(i), position=(0, 0, z),
                            center_frequency=500, bandwidth=500,
                            resistance=0, effective_height=1,
                            trigger_threshold=0, noisy=False)
kernel = pyrex.EventKernel(generator=particle_generator,
                           ice_model=pyrex.IceModel,
                           antennas=detector)
triggered = False
while not triggered:
   kernel.event()
    for antenna in detector:
        if antenna.is_hit:
           triggered = True
           break
for antenna in detector:
    for i, wave in enumerate(antenna.waveforms):
        plt.plot(wave.times * 1e9, wave.values)
        plt.xlabel("Time (ns)")
        plt.ylabel("Voltage (V)")
        plt.title(antenna.name + " - waveform "+str(i))
```

2.7 More Examples

For more code examples, see the PyREx Demo python notebook.

2.6. Full Simulation 9

CHAPTER

THREE

PYREX API

3.1 Package contents

```
class pyrex.Signal (times, values)
```

Base class for signals. Takes arrays of times and values (values array forced to size of times array by zero padding or slicing). Supports adding between signals with the same time values, resampling the signal, and calculating the signal's envelope.

dt

Returns the spacing of the time array, or None if invalid.

envelope

Calculates envelope of the signal by Hilbert transform.

resample(n)

Resamples the signal into n points in the same time range.

spectrum

Returns the FFT spectrum of the signal.

frequencies

Returns the FFT frequencies of the signal.

filter_frequencies (freq_response)

Applies the given frequency response function to the signal.

```
class pyrex.EmptySignal (times)
```

```
Bases: pyrex.signals.Signal
```

Class for signal with no amplitude (all values = 0)

class pyrex.FunctionSignal (times, function)

```
Bases: pyrex.signals.Signal
```

Class for signals generated by a function

pyrex.AskaryanSignal

alias of FastAskaryanSignal

```
class pyrex.signals.FastAskaryanSignal (times, energy, theta, n=1.78, t0=0)
```

```
Bases: pyrex.signals.Signal
```

Askaryan pulse binned to times from neutrino with given energy (TeV) observed at angle theta (radians). Optional parameters are the index of refraction n, and pulse offset to start time t0 (s). Returned signal values are electric fields (V/m).

Note that the amplitude of the pulse goes as 1/R, where R is the distance from source to observer. R is assumed to be 1 meter so that dividing by a different value produces the proper result.

vector potential

Recover the vector_potential from the electric field. Mostly just for testing purposes.

RAC (time)

Calculates R * vector potential (A) at the Cherenkov angle in Vs at the given time (s).

```
charge_profile (z, density=0.92, crit_energy=7.86e-05, rad_length=36.08)
```

Calculates the longitudinal charge profile in the EM shower at distance z (m) with parameters for the density (g/cm³), critical energy (TeV), and electron radiation length (g/cm²) in ice.

```
max_length (density=0.92, crit_energy=7.86e-05, rad_length=36.08)
```

Calculates the maximum length (m) of an EM shower with parameters for the density (g/cm³), critical energy (TeV), and electron radiation length (g/cm²) in ice.

 ${f class}$ pyrex. ThermalNoise (times, temperature, resistance, f_band, f_amplitude=1, n_freqs=0)

```
Bases: pyrex.signals.Signal
```

Thermal Rayleigh noise at a given temperature (K) and resistance (ohms) in the frequency band $f_{min,f_{max}}$ (Hz). Optional parameters are $f_{min,f_{max}}$ (Hz). Optional parameters are $f_{min,f_{max}}$ (Hz) which can be a number or a function designating the amplitudes at each frequency, and $f_{min,f_{max}}$ (default is based on the FFT bin size of given times array). Returned signal values are voltages (V).

class pyrex . Antenna (position, temperature, freq_range, resistance=None, noisy=True)

Base class for an antenna with a given position (m), temperature (K), allowable frequency range (Hz), total resistance (ohm) used for Johnson noise, and whether or not to include noise in the antenna's waveforms. Defines default trigger, frequency response, and signal reception functions that can be overwritten in base classes to customize the antenna.

is hit

Test for whether the antenna has received a signal.

isHit()

Deprecated. Replaced by is_hit property.

clear(

Reset the antenna to a state of having received no signals.

waveforms

Signal + noise (if noisy) at each triggered antenna hit.

all waveforms

Signal + noise (if noisy) at all antenna hits, even those that didn't trigger.

trigger (signal)

Function to determine whether or not the antenna is triggered by the given Signal object.

response (frequencies)

Function to return the frequency response of the antenna at the given frequencies (Hz). This function should return the response as imaginary numbers, where the real part is the amplitude response and the imaginary part is the phase response.

```
receive (signal, polarization=[0, 0, 1])
```

Process incoming signal according to the filter function and store it to the signals list. Subclasses may extend this fuction, but should end with super().receive(signal).

class pyrex.**DipoleAntenna** (name, position, center_frequency, bandwidth, resistance, effective_height, polarization=[0, 0, 1], trigger_threshold=0, noisy=True)

```
Bases: pyrex.antenna. Antenna
```

Antenna with a given name, position (m), center frequency (MHz), bandwidth (MHz), resistance (ohm), effective height (m), polarization direction, and trigger threshold (V).

trigger (signal) Trigger on the signal if the maximum signal value is above the given threshold. response (frequencies) Butterworth filter response for the antenna's frequency range. receive (signal, polarization=[0, 0, 1]) Apply polarization effect to signal, then proceed with usual antenna reception. pyrex.IceModel alias of AntarcticIce class pyrex.ice_model.AntarcticIce Bases: object Class containing characteristics of ice at the south pole. k = 0.438a = 0.0132n0 = 1.32thickness = 2850classmethod gradient (z) Returns the gradient of the index of refraction at depth z (m). classmethod index (z) Returns the medium's index of refraction, n, at depth z (m). static temperature (z) Returns the temperature (K) of the ice at depth z (m) classmethod attenuation_length (z, f)Returns the attenuation length at depth z (m) and frequency f (MHz). pyrex.prem_density(r) Returns the earth's density (g/cm³) for a given radius r (m). Calculated by the Preliminary Earth Model (PREM). pyrex.slant_depth (angle, depth, step=5000) Returns the material thickness (g/cm²) for a chord cutting through earth at Nadir angle and starting at depth (m). class pyrex.Particle Named tuple for containing particle attributes. Consists of a 3-D vertex (m), 3-D direction vector, and an energy (GeV). direction energy vertex **class** pyrex. **ShadowGenerator** (*dx*, *dy*, *dz*, *energy_generator*) Class to generate UHE neutrino vertices in (relatively) shallow detectors. Takes into accout Earth shadowing

(sort of). energy_generator should be a function that returns a particle energy in GeV.

Creates a particle with random vertex in cube and random direction.

class pyrex.PathFinder (ice_model, from_point, to_point)

create_particle()

Class for ray tracking.

exists

Boolean of whether path exists.

emitted_ray

Direction in which ray is emitted.

path_length

Length of the path (m).

tof

Time of flight (s) for a particle along the path. Calculated using default values of self.time_of_flight()

```
time_of_flight (n_steps=10)
```

Time of flight (s) for a particle along the path.

```
attenuation (f, n\_steps=10)
```

Returns the attenuation factor for a signal of frequency f (Hz) traveling along the path.

propagate (signal)

Applies attenuation to the signal along the path.

class pyrex.EventKernel (generator, ice model, antennas)

Kernel for generation of events with a given particle generator, ice model, and list of antennas.

event()

Generate particle, propagate signal through ice to antennas, process signal at antennas, and return the original particle.

3.2 Submodules

3.2.1 pyrex.signals module

Module containing classes for digital signal processing

```
class pyrex.signals.Signal (times, values)
     Bases: object
```

Base class for signals. Takes arrays of times and values (values array forced to size of times array by zero padding or slicing). Supports adding between signals with the same time values, resampling the signal, and calculating the signal's envelope.

dt

Returns the spacing of the time array, or None if invalid.

envelope

Calculates envelope of the signal by Hilbert transform.

resample(n)

Resamples the signal into n points in the same time range.

spectrum

Returns the FFT spectrum of the signal.

frequencies

Returns the FFT frequencies of the signal.

filter_frequencies (freq_response)

Applies the given frequency response function to the signal.

```
class pyrex.signals.EmptySignal (times)
    Bases: pyrex.signals.Signal
    Class for signal with no amplitude (all values = 0)

class pyrex.signals.FunctionSignal (times, function)
    Bases: pyrex.signals.Signal
    Class for signals generated by a function

class pyrex.signals.SlowAskaryanSignal (times, energy, theta, n=1.78, t0=0)
```

Askaryan pulse binned to times from neutrino with given energy (TeV) observed at angle theta (radians). Optional parameters are the index of refraction n, and pulse offset to start time t0 (s). Returned signal values are electric fields (V/m).

Note that the amplitude of the pulse goes as 1/R, where R is the distance from source to observer. R is assumed to be 1 meter so that dividing by a different value produces the proper result.

RAC (time)

Bases: pyrex.signals.Signal

Calculates R * vector potential at the Cherenkov angle in Vs at the given time (s).

```
charge_profile (z, density=0.92, crit_energy=7.86e-05, rad_length=36.08)
```

Calculates the longitudinal charge profile in the EM shower at distance z (m) with parameters for the density (g/cm^3), critical energy (TeV), and electron radiation length (g/cm^2) in ice.

```
max_length (density=0.92, crit_energy=7.86e-05, rad_length=36.08)
```

Calculates the maximum length (m) of an EM shower with parameters for the density (g/cm³), critical energy (TeV), and electron radiation length (g/cm²) in ice.

```
class pyrex.signals.FastAskaryanSignal (times, energy, theta, n=1.78, t0=0)
    Bases: pyrex.signals.Signal
```

Askaryan pulse binned to times from neutrino with given energy (TeV) observed at angle theta (radians). Optional parameters are the index of refraction n, and pulse offset to start time t0 (s). Returned signal values are electric fields (V/m).

Note that the amplitude of the pulse goes as 1/R, where R is the distance from source to observer. R is assumed to be 1 meter so that dividing by a different value produces the proper result.

vector_potential

Recover the vector_potential from the electric field. Mostly just for testing purposes.

RAC (time

Calculates R * vector potential (A) at the Cherenkov angle in Vs at the given time (s).

```
charge profile (z, density=0.92, crit\ energy=7.86e-05, rad\ length=36.08)
```

Calculates the longitudinal charge profile in the EM shower at distance z (m) with parameters for the density (g/cm³), critical energy (TeV), and electron radiation length (g/cm²) in ice.

```
max_length (density=0.92, crit_energy=7.86e-05, rad_length=36.08)
```

Calculates the maximum length (m) of an EM shower with parameters for the density (g/cm³), critical energy (TeV), and electron radiation length (g/cm²) in ice.

```
pyrex.signals.AskaryanSignal
    alias of FastAskaryanSignal

class pyrex.signals.GaussianNoise (times, sigma)
    Bases: pyrex.signals.FunctionSignal
```

Gaussian noise signal with standard deviation sigma

3.2. Submodules

```
class pyrex.signals.ThermalNoise (times, temperature, resistance, f\_band, f\_amplitude=1, n\_freqs=0)
```

Bases: pyrex.signals.Signal

Thermal Rayleigh noise at a given temperature (K) and resistance (ohms) in the frequency band f_band=[f_min,f_max] (Hz). Optional parameters are f_amplitude (default 1) which can be a number or a function designating the amplitudes at each frequency, and n_freqs which is the number of frequencies to use (in f_band) for the calculation (default is based on the FFT bin size of given times array). Returned signal values are voltages (V).

3.2.2 pyrex.antenna module

Module containing antenna class capable of receiving signals

```
class pyrex.antenna.Antenna (position, temperature, freq_range, resistance=None, noisy=True)
    Bases: object
```

Base class for an antenna with a given position (m), temperature (K), allowable frequency range (Hz), total resistance (ohm) used for Johnson noise, and whether or not to include noise in the antenna's waveforms. Defines default trigger, frequency response, and signal reception functions that can be overwritten in base classes to customize the antenna.

is hit

Test for whether the antenna has received a signal.

isHit()

Deprecated. Replaced by is_hit property.

clear()

Reset the antenna to a state of having received no signals.

waveforms

Signal + noise (if noisy) at each triggered antenna hit.

all_waveforms

Signal + noise (if noisy) at all antenna hits, even those that didn't trigger.

trigger (signal)

Function to determine whether or not the antenna is triggered by the given Signal object.

```
response (frequencies)
```

Function to return the frequency response of the antenna at the given frequencies (Hz). This function should return the response as imaginary numbers, where the real part is the amplitude response and the imaginary part is the phase response.

```
receive (signal, polarization=[0, 0, 1])
```

Process incoming signal according to the filter function and store it to the signals list. Subclasses may extend this fuction, but should end with super().receive(signal).

Bases: pyrex.antenna.Antenna

Antenna with a given name, position (m), center frequency (MHz), bandwidth (MHz), resistance (ohm), effective height (m), polarization direction, and trigger threshold (V).

```
trigger (signal)
```

Trigger on the signal if the maximum signal value is above the given threshold.

```
response (frequencies)
```

Butterworth filter response for the antenna's frequency range.

```
receive (signal, polarization=[0, 0, 1])
```

Apply polarization effect to signal, then proceed with usual antenna reception.

3.2.3 pyrex.ice_model module

Module containing ice model. AntarcticIce class contains static and class methods for easy swapping of models. IceModel class is set to the preferred ice model.

```
class pyrex.ice_model.AntarcticIce
    Bases: object
    Class containing characteristics of ice at the south pole.
    k = 0.438
    a = 0.0132
```

thickness = 2850

n0 = 1.32

classmethod gradient (z)

Returns the gradient of the index of refraction at depth z (m).

classmethod index (z)

Returns the medium's index of refraction, n, at depth z (m).

```
static temperature (z)
```

Returns the temperature (K) of the ice at depth z (m)

```
classmethod attenuation_length (z, f)
```

Returns the attenuation length at depth z (m) and frequency f (MHz).

```
class pyrex.ice_model.NewcombIce
    Bases: pyrex.ice_model.AntarcticIce
```

Class inheriting from AntarcticIce, with new attenuation_length function based on Matt Newcomb's fit (DOESN'T CURRENTLY WORK - USE ANTARCTICICE).

```
classmethod attenuation_length (z, f)
```

Returns the attenuation length at depth z (m) and frequency f (MHz) by Matt Newcomb's fit (DOESN'T CURRENTLY WORK - USE BOGORODSKY).

```
pyrex.ice_model.IceModel alias of AntarcticIce
```

3.2.4 pyrex.earth_model module

Module containing earth model. Uses PREM for density as a function of radius and a simple integrator for calculation of the slant depth as a function of nadir angle.

```
pyrex.earth_model.prem_density (r)
Returns the earth's density (g/cm^3) for a given radius r (m). Calculated by the Preliminary Earth Model (PREM).
```

```
pyrex.earth_model.slant_depth (angle, depth, step=5000)
```

Returns the material thickness (g/cm²) for a chord cutting through earth at Nadir angle and starting at depth (m).

3.2. Submodules

3.2.5 pyrex.particle module

Module for particles (namely neutrinos) and neutrino interactions in the ice. Interactions include Earth shadowing (absorption) effect.

```
class pyrex.particle.NeutrinoInteraction (c, p)
     Bases: object
     Class for neutrino interaction attributes.
     cross\_section(E)
          Return the cross section at a given energy E (GeV).
     interaction length (E)
          Return the interaction length at a given energy E (GeV).
class pyrex.particle.Particle
     Bases: tuple
     Named tuple for containing particle attributes. Consists of a 3-D vertex (m), 3-D direction vector, and an energy
     direction
     energy
     vertex
pyrex.particle.random_direction()
     Generate an arbitrary 3D unit vector.
class pyrex.particle.ShadowGenerator(dx, dy, dz, energy_generator)
     Bases: object
     Class to generate UHE neutrino vertices in (relatively) shallow detectors. Takes into accout Earth shadowing
     (sort of). energy_generator should be a function that returns a particle energy in GeV.
     create_particle()
```

3.2.6 pyrex.ray tracing module

Module containing class for ray tracking through the ice. Ray tracing not yet implemented.

Creates a particle with random vertex in cube and random direction.

```
class pyrex.ray_tracing.PathFinder (ice_model, from_point, to_point)
    Bases: object
    Class for ray tracking.
    exists
        Boolean of whether path exists.

emitted_ray
        Direction in which ray is emitted.

path_length
        Length of the path (m).

tof
        Time of flight (s) for a particle along the path. Calculated using default values of self.time_of_flight()
        time_of_flight (n_steps=10)
        Time of flight (s) for a particle along the path.
```

```
attenuation (f, n\_steps=10)
```

Returns the attenuation factor for a signal of frequency f (Hz) traveling along the path.

```
propagate (signal)
```

Applies attenuation to the signal along the path.

3.2.7 pyrex.kernel module

Module for the simulation kernel. Includes neutrino generation, ray tracking (no raytracing yet), and hit generation.

```
{\bf class}~{\tt pyrex.kernel.EventKernel}~({\it generator}, ice\_{\it model}, {\it antennas})
```

Bases: object

Kernel for generation of events with a given particle generator, ice model, and list of antennas.

event (

Generate particle, propagate signal through ice to antennas, process signal at antennas, and return the original particle.

3.2. Submodules

FOUR

VERSION HISTORY

4.1 Version 1.0.1

• Fixed bugs in AskaryanSignal that caused the convolution to fail

4.2 Version 1.0.0

- Created PyREx package based on original notebook
- · Added all signal classes to produce full-waveform Askaryan pulses and thermal noise
- Changed Antenna class to DipoleAntenna to allow Antenna to be a base class
- Changed Antenna.isHit() method to Antenna.is_hit property
- Introduced IceModel alias for AntarcticIce (or any future preferred ice model)
- Moved AntarcticIce.attenuationLengthMN to its own NewcombIce class inheriting from AntarcticIce
- Added PathFinder.propagate() to propagate a Signal object in a customizable way
- Changed naming conventions to be more consistent, verbose, and "pythonic":
 - AntarcticIce.attenuationLength() becomes AntarcticIce.
 attenuation_length()
 - In pyrex.earth_model, RE becomes EARTH_RADIUS
 - $In\ pyrex.particle$, $neutrino_interaction\ becomes\ NeutrinoInteraction$
 - In pyrex.particle, NA becomes AVOGADRO NUMBER
 - particle class becomes Particle namedtuple
 - * Particle.vtx becomes Particle.vertex
 - * Particle.dir becomes Particle.direction
 - * Particle.E becomes Particle.energy
 - In pyrex.particle, next_direction() becomes random_direction()
 - shadow_generator becomes ShadowGenerator
 - PathFinder methods become properties where reasonable:
 - * PathFinder.exists() becomes PathFinder.exists

- * PathFinder.getEmittedRay() becomes PathFinder.emitted_ray
- * PathFinder.getPathLength() becomes PathFinder.path_length
- PathFinder.propagateRay() split into PathFinder.time_of_flight() (with corresponding PathFinder.tof property) and PathFinder.attenuation()

4.3 Version 0.0.0

Original PyREx python notebook written by Kael Hanson

PYTHON MODULE INDEX

р

pyrex,11
pyrex.antenna,16
pyrex.earth_model,17
pyrex.ice_model,17
pyrex.kernel,19
pyrex.particle,18
pyrex.ray_tracing,18
pyrex.signals,14

24 Python Module Index

INDEX

A	energy (pyrex.Particle attribute), 13								
a (pyrex.ice_model.AntarcticIce attribute), 13, 17	energy (pyrex.particle.Particle attribute), 18								
all_waveforms (pyrex.Antenna attribute), 12	envelope (pyrex.Signal attribute), 11								
all_waveforms (pyrex.antenna.Antenna attribute), 16	envelope (pyrex.signals.Signal attribute), 14								
AntarcticIce (class in pyrex.ice_model), 13, 17	event() (pyrex.EventKernel method), 14								
Antenna (class in pyrex), 12	event() (pyrex.kernel.EventKernel method), 19								
Antenna (class in pyrex.antenna), 16	EventKernel (class in pyrex), 14								
AskaryanSignal (in module pyrex), 11	EventKernel (class in pyrex.kernel), 19								
AskaryanSignal (in module pyrex.signals), 15	exists (pyrex.PathFinder attribute), 13								
attenuation() (pyrex.PathFinder method), 14	exists (pyrex.ray_tracing.PathFinder attribute), 18								
attenuation() (pyrex.ray_tracing.PathFinder method), 18	F								
attenuation_length() (pyrex.ice_model.AntarcticIce class	•								
method), 13, 17	FastAskaryanSignal (class in pyrex.signals), 11, 15								
attenuation_length() (pyrex.ice_model.NewcombIce	filter_frequencies() (pyrex.Signal method), 11								
class method), 17	filter_frequencies() (pyrex.signals.Signal method), 14								
	frequencies (pyrex.Signal attribute), 11								
C	frequencies (pyrex.signals.Signal attribute), 14								
charge_profile() (pyrex.signals.FastAskaryanSignal	FunctionSignal (class in pyrex), 11								
method), 12, 15	FunctionSignal (class in pyrex.signals), 15								
charge_profile() (pyrex.signals.SlowAskaryanSignal	G								
method), 15	<u>-</u>								
clear() (pyrex.Antenna method), 12	GaussianNoise (class in pyrex.signals), 15								
clear() (pyrex.antenna.Antenna method), 16	gradient() (pyrex.ice_model.AntarcticIce class method),								
create_particle() (pyrex.particle.ShadowGenerator	13, 17								
method), 18									
create_particle() (pyrex.ShadowGenerator method), 13	IceModel (in module pyrex), 13								
cross_section() (pyrex.particle.NeutrinoInteraction	IceModel (in module pyrex.ice_model), 17								
method), 18	index() (pyrex.ice_model.AntarcticIce class method), 13,								
D	17								
D	interaction_length() (pyrex.particle.NeutrinoInteraction								
DipoleAntenna (class in pyrex), 12	method), 18								
DipoleAntenna (class in pyrex.antenna), 16	is_hit (pyrex.Antenna attribute), 12								
direction (pyrex.Particle attribute), 13	is_hit (pyrex.antenna.Antenna attribute), 16								
direction (pyrex.particle.Particle attribute), 18	isHit() (pyrex.Antenna method), 12								
dt (pyrex.Signal attribute), 11	isHit() (pyrex.antenna.Antenna method), 16								
dt (pyrex.signals.Signal attribute), 14									
-	K								
E	k (pyrex.ice_model.AntarcticIce attribute), 13, 17								
emitted_ray (pyrex.PathFinder attribute), 14	N.A.								
emitted_ray (pyrex.ray_tracing.PathFinder attribute), 18	M								
EmptySignal (class in pyrex), 11	max_length() (pyrex.signals.FastAskaryanSignal								
EmptySignal (class in pyrex.signals), 14	method), 12, 15								

```
max length()
                                                         spectrum (pyrex.signals.Signal attribute), 14
                     (pyrex.signals.SlowAskaryanSignal
         method), 15
Ν
                                                                            (pyrex.ice model.AntarcticIce
                                                          temperature()
                                                                                                             static
n0 (pyrex.ice_model.AntarcticIce attribute), 13, 17
                                                                    method), 13, 17
NeutrinoInteraction (class in pyrex.particle), 18
                                                          ThermalNoise (class in pyrex), 12
NewcombIce (class in pyrex.ice_model), 17
                                                          ThermalNoise (class in pyrex.signals), 15
                                                          thickness (pyrex.ice_model.AntarcticIce attribute), 13, 17
Р
                                                          time of flight() (pyrex.PathFinder method), 14
                                                          time of flight() (pyrex.ray tracing.PathFinder method),
Particle (class in pyrex), 13
                                                                    18
Particle (class in pyrex.particle), 18
                                                          tof (pyrex.PathFinder attribute), 14
path length (pyrex.PathFinder attribute), 14
                                                          tof (pyrex.ray_tracing.PathFinder attribute), 18
path_length (pyrex.ray_tracing.PathFinder attribute), 18
                                                          trigger() (pyrex.Antenna method), 12
PathFinder (class in pyrex), 13
                                                          trigger() (pyrex.antenna.Antenna method), 16
PathFinder (class in pyrex.ray tracing), 18
                                                          trigger() (pyrex.antenna.DipoleAntenna method), 16
prem density() (in module pyrex), 13
                                                          trigger() (pyrex.DipoleAntenna method), 12
prem density() (in module pyrex.earth model), 17
propagate() (pyrex.PathFinder method), 14
propagate() (pyrex.ray_tracing.PathFinder method), 19
pyrex (module), 11
                                                          vector potential (pyrex.signals.FastAskaryanSignal at-
pyrex.antenna (module), 16
                                                                    tribute), 11, 15
pyrex.earth_model (module), 17
                                                          vertex (pyrex.Particle attribute), 13
pyrex.ice_model (module), 17
                                                          vertex (pyrex.particle.Particle attribute), 18
pyrex.kernel (module), 19
                                                          W
pyrex.particle (module), 18
pyrex.ray_tracing (module), 18
                                                          waveforms (pyrex.Antenna attribute), 12
pyrex.signals (module), 14
                                                          waveforms (pyrex.antenna.Antenna attribute), 16
R
RAC() (pyrex.signals.FastAskaryanSignal method), 12,
RAC() (pyrex.signals.SlowAskaryanSignal method), 15
random direction() (in module pyrex.particle), 18
receive() (pyrex.Antenna method), 12
receive() (pyrex.antenna.Antenna method), 16
receive() (pyrex.antenna.DipoleAntenna method), 17
receive() (pyrex.DipoleAntenna method), 13
resample() (pyrex.Signal method), 11
resample() (pyrex.signals.Signal method), 14
response() (pyrex.Antenna method), 12
response() (pyrex.antenna.Antenna method), 16
response() (pyrex.antenna.DipoleAntenna method), 16
response() (pyrex.DipoleAntenna method), 13
S
ShadowGenerator (class in pyrex), 13
ShadowGenerator (class in pyrex.particle), 18
Signal (class in pyrex), 11
Signal (class in pyrex.signals), 14
slant_depth() (in module pyrex), 13
slant_depth() (in module pyrex.earth_model), 17
SlowAskaryanSignal (class in pyrex.signals), 15
spectrum (pyrex.Signal attribute), 11
```

26 Index